

---

## Name

rdairplay — Module for playing Rivendell logs

## Synopsis

rdairplay [*OPTIONS*]

## Description

The **rdairplay**(1) module is the primary interface for executing logs other audio content. This man page documents its command-line arguments. For overview of the UI and other elements, see the *Running Logs with RDAirPlay* chapter in the *Rivendell Operations and Administration Guide*.

## Options

|                                               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|-----------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>log-spec=log-name[:next-line[+]]</code> | After startup, load the <i>log-name</i> log into the log machine specified by <i>log-spec</i> . If a <i>next-line</i> value has been specified, then do a <b>make next</b> to that line. If a <b>+</b> has been appended to the line number, then start the log.<br><br><i>log-spec</i> must be <b>--log1</b> , <b>--log2</b> or <b>--log3</b> , referring to the Main Log, Aux 1 Log or Aux 2 Log log machines respectively. It is possible to use multiple <i>log-spec</i> clauses. If multiple clauses referring to the same log machine are given, then the last one specified will be used. |
| <code>--dump-panel-updates</code>             | When this option is given, <b>rdairplay</b> (1) will print a dump of the currently loaded sound panel array to standard output each time the Rivendell user logged into the system is changed.                                                                                                                                                                                                                                                                                                                                                                                                   |

## Examples

|                                                    |                                                                                                     |
|----------------------------------------------------|-----------------------------------------------------------------------------------------------------|
| <code>rdairplay --log1=MyLog</code>                | Load <b>MyLog</b> into the Main Log machine                                                         |
| <code>rdairplay --log2=My-Log:14+</code>           | Load <b>MyLog</b> into the Aux Log 1 machine, 'Make Next' to line <b>14</b> and then start the log. |
| <code>rdairplay --log1=YourLog --log2=MyLog</code> | Load <b>YourLog</b> into the Main Log machine and <b>MyLog</b> into the Aux Log 1 machine.          |